



## FIELD OF DREAMS

FREE PATTERN • 521/2" x 40" • By Northcott Studio

Northcott Canada 101 Courtland Avenue Vaughan, Ontario L4K 3T5 Northcott USA 1050 Valley Brook Avenue Lyndhurst, NJ 07071



## Field of Dreams

Fabric Collection: **Forage & Fodder** Finished Size: Approximately 52 ½" x 40" WOF = width of fabric All seams are sewn using a ¼" seam allowance

Fabric Requirements	Yardage	Cutting Instructions
<b>Fabric A</b> – Main Print 40096-54	1 1/3 yds	<ul> <li>Trim selvage edges</li> <li>Cut 4 – 10 ½" x WOF Focus Strips, keeping strips in the order in which they are cut.</li> </ul>
Fabric B - Shadow 40009-12 (gold)	1/3 yd	• Cut 5 – 1 ½" x WOF strips
<b>Fabric C</b> – Background 40094-87 (Sumac) OR 40095-74 (Hickory Sky)	1 1/8 yds	<ul> <li>Cut 2 - 2 1/2" x WOF strips (outer vertical side strips)</li> <li>Cut 3 - 2" x WOF strips (vertical sashing strips)</li> <li>Cut 2 - 11 1/2" x WOF strips; Sub-Cut: <ul> <li>2 - 11 1/2" x 10 1/2" rectangles</li> <li>2 - 11 1/2" x 7 1/2" rectangles</li> <li>2 - 11 1/2" x 4 1/2" rectangles</li> <li>2 - 11 1/2" x 2 1/2" rectangles</li> <li>8 - 1 1/2" squares</li> </ul> </li> </ul>
<b>Fabric D</b> – Binding 40009-12 (gold)	3/8 yd	• Cut 5 – 2 1/4" x WOF strips
<b>Fabric E</b> – Backing 40094-87 (Sumac) OR 40095-74 (Hickory Sky)	1 3/4 yds	No cutting required.

## Assembly Instructions:

- Referring to Diagram 1, measure and mark 33 ½" from the <u>bottom</u> of Focus Strip 1 and cut at this marked line.
- 2. Measure and mark 33 ½" from the top of Focus Strip 2 and cut at this marked line.
- 3. Cut 5" off the <u>bottom</u> edge of Focus Strip 3. Then measure and mark 22 ½" from the <u>bottom</u> and cut at this marked line. Repeat for Focus Strip 4.
- 4. Prepare the 1 ½" Fabric B strips by cutting two strips to 33 ½", two strips to 22 ½" and four strips to 11 ½".
- 5. Draw a diagonal line on the wrong side of the 8 1 ½" squares. Place a square at the top of each long vertical strip and the left edge of each short horizontal strip with right sides together (as shown in Diagram 2) and sew along the drawn lines. Trim ¼" from the sewn lines and press corners out.








Diagram 2

- 6. Sew the long vertical strips to the right side of the focus strips, then sew the short horizontal strips to the bottom edges.
- 7. Add one 11 ½" x 2 ½" rectangle to the bottom and one 11 ½" x 4 ½" rectangle to the top of Focus Strip 1.
- 8. Add one 11 ½" x 4 ½" rectangle to the bottom and one 11 ½" x 2 ½" rectangle to the top of Focus Strip 2.
- 9. Add one 11 ½" x 7 ½" rectangle to the bottom and one 11 ½" x 10 ½" rectangle to the top of Focus Strips 3 & 4.
- 10. Trim the  $3 2^{"}$  vertical sashing strips to  $40^{"}$  in length.
- 11. Sew the Focus Strips together with a vertical sashing strip between each one.
- 12. Trim the  $2 2\frac{1}{2}$  outer vertical strips to 40" in length. Add one to each side to complete the quilt top.
- 13. Layer quilt top with batting and backing. Quilt as desired.
- 14. Prepare binding strips and bind using your favorite method.