




NORTHCOTT
Cottons that feel like silk

STONEHENGE CANYON RIDGE

by Linda Ludovico
Pattern by Patti Carey



Cabin In The Canyon

68 1/2" x 86 1/2"

by Patti Carey

www.northcott.com

Northcott Canada

101 Courtland Avenue
Vaughan, Ontario L4K 3T5
1.800.268.1466

Northcott USA

1099 Wall St. West, Suite 354
Lyndhurst, NJ 07071
1.800.223.6337

www.northcott.com

Cabin in the Canyon

Designed by Patti Carey using Northcott's Stonehenge *Canyon Ridge* collection

Finished Size: 68½" x 86½"

Number of Blocks & Finished Size: 24 brown & 24 rust blocks, all 9" finished

Wof = width of fabric

Fabric Requirements	Yards	Cutting Instructions
A – lengthwise border stripe #39133-37	1⅞yds	◇ Cut 4 lengthwise strips 9⅞" wide; cut into (24) 9⅞" squares. Cut 12 squares once diagonally from top right to bottom left, and 12 squares once diagonally from top left to bottom right.
B – outer border #39134-37	1⅞yds	◇ Cut 8 strips 6½" x wof; join end-to-end in pairs, and trim 2 to 74½" and 2 to 68½".
C – darkest brown - inner border & blocks #39140-37	1⅞yds	◇ Cut 7 strips 1½" x wof; join end-to-end and cut (2) 72½" pieces & (2) 56½" pieces. ◇ Cut 1 strip 8¾" x wof & 1 strip 9¾" x wof; cross-cut each strip into (24) 1½" pieces. ◇ Cut 9 strips 2½" x wof; join end-to-end, press in half and reserve for binding
D – brown 2 nd darkest round #39080-37	½yd	◇ Cut 1 strip 6¾" x wof & 1 strip 7¾" x wof; cross-cut each strip into (24) 1½" pieces.
E – brown 3 rd darkest round #39060-53	⅝yd	◇ Cut 1 strip 4¾" x wof & 1 strip 5¾" x wof; cross-cut each strip into (24) 1½" pieces.
F – brown lightest round #3934-12	¼yd	◇ Cut 1 strip 2¾" x wof & 1 strip 3¾" x wof; cross-cut each strip into (24) 1½" pieces.
G – block center #39139-37	¼yd	◇ Cut 3 strips 1¾" x wof; cut into (48) 1¾" squares.
H – dark rust #39060-37	⅝yd	◇ Cut 1 strip 8¾" x wof & 1 strip 9¾" x wof; cross-cut each strip into (24) 1½" pieces.
I – 2 nd darkest rust round #39137-37	½yd	◇ Cut 1 strip 6¾" x wof & 1 strip 7¾" x wof; cross-cut each strip into (24) 1½" pieces.
J – 3 rd darkest rust round #39136-37	⅝yd	◇ Cut 1 strip 4¾" x wof & 1 strip 5¾" x wof; cross-cut each strip into (24) 1½" pieces.
K – rust lightest round #3954-151	¼yd	◇ Cut 1 strip 2¾" x wof & 1 strip 3¾" x wof; cross-cut each strip into (24) 1½" pieces.
Backing	5⅞yds	◇ Cut into 2 equal lengths and join edge-to-edge.
Batting	A piece 72" x 90"	

Piecing:

1. Lay out all of the brown block pieces in order from shortest to longest (F, E, D, & C).




Diagram 1




Diagram 2




Diagram 3




Diagram 4

2. Sew a 2¾" F piece onto 24 G squares, aligning one end with square. Press seam toward F.

3. Sew the 3¾" F piece onto adjacent side of G as shown; press seam toward F.

4. Continue, adding the shorter E, longer E, shorter D, longer D, shorter C, then longer C pieces.

5. Repeat steps 1-4 using the rust block pieces (K, J, I & H).

6. Divide the half-log cabin units into 4 piles, placing 6 rust and 6 brown units in each pile.

7. Arrange the A triangles into 4 piles: top right, bottom left, top left, and bottom right.
8. Working with one A pile and one rust/brown pile at a time, place an A triangle right side down on each rust or brown half-log cabin unit, aligning the straight edges. Stitch $\frac{1}{4}$ " from the angled edge of the triangle. Trim off excess points of the half-log cabin, and press seam toward A.

Assembly:

1. Using the photo as a guide, lay out the blocks in concentric rows of rust and brown, using all of the top right blocks in the top right corner of the quilt, the top left ones in the top left corner and so on.
2. Sew the blocks into rows, then sew the rows together.
3. Sew the $72\frac{1}{2}$ " C strips to each side, then the $56\frac{1}{2}$ " C strips to top and bottom edges, pressing seams toward C.
4. Sew the $74\frac{1}{2}$ " B strips to each side, then the $68\frac{1}{2}$ " B strips to top and bottom edges, pressing seams toward B.

Finishing:

Layer the prepared backing, batting and quilt top. Baste and quilt as desired. Trim edges even with quilt top. Sew the prepared binding to the edges, turn and stitch in place.