


SADDLE UP

by Ellen Clark Designs



NORTHCOTT
Cottons that feel like silk



SADDLE UP RUNNER

FREE PATTERN • By Northcott Studio

Finished Size 17" x 66 1/2"

Northcott Canada
101 Courtland Avenue
Vaughan, Ontario L4K 3T5

Northcott USA
1050 Valley Brook Ave,
Lyndhurst, NJ 07071

www.northcott.com





Saddle Up Runner

Collection: **Saddle Up**

Finished Size: 17" x 66 ½"



WOF = width of fabric

All seams are sewn using a ¼" seam allowance

Fabric requirements	Yardage	Cutting Instructions
 <p>Fabric A DP24382-36</p>	1 - 24" Panel	<ul style="list-style-type: none"> From the panel, trim the two placemats to 13" x 21 ½" each From the panel, trim the six blocks to 6 ½" x 6 ½" (you will have to cut into the block so fussy cutting is suggested)
 <p>Fabric B 24389-12</p>	3/8 yard	<ul style="list-style-type: none"> Cut 2 – 1" x WOF strips Sub-cut 6 – 1" x 13" strips & 3 – 1" x 6 ½" strips Cut 4 – 2 ½" x WOF strips
 <p>Fabric C 24388-35</p>	3/8 yard	<ul style="list-style-type: none"> Cut 5 – 2 ¼" x WOF strips for binding Join the strips using a diagonal seam; fold in half with wrong sides together along the length of the strip and press.
 <p>Backing DP24384-14</p>	1 yard	<ul style="list-style-type: none"> Cut in half across LOF to get two (2) – 21 ½" x 36" pieces Sew the pieces together along the short edges

Runner Assembly:

- Sew a 1" x 6 ½" Fabric B strip between two 6 ½" panel blocks to make one Block Unit, as shown. Make 3 Block Units using the six panel blocks.
- Arrange the Block Units between and on outer sides of the two placemat pieces, adding a 1" x 13" Fabric B sashing strip between each, as shown.



- Join the four Fabric B 2 ½" x WOF strips end-to-end. Cut 2 – 2 ½" x 62" border strips and sew to the top & bottom. Cut 2 – 2 ½" x 17" border strips and sew one to each side.
- Layer top, batting & backing. Quilt & bind as desired. Your Runner is complete!